


How to forward calls to Hunt Groups and seats in the Customer Administration Portal

To enable call forwarding, follow the instructions below:

Hunt Groups

Hunt groups have a call forward setting available on the right side of the Hunt Group configuration window.

1. In the **Customer Administration Portal**, select **Enterprise Services**.
2. Select **Hunt Groups**.
3. Locate the **Hunt Group** you wish to affect and press **Edit**.
4. On the top right side of the new window is a section labeled **Call Forwarding Options**.
5. Enter the number or extension where you would like to forward the calls in the **Destination Number** field. This can be a ten digit number outside of your network or an internal extension.
6. You can also set how many seconds the users have to accept the call in the field above. This has to be a positive value, but 1 second will virtually forward it instantly.
7. Save at the bottom and the changes will apply immediately.



The screenshot shows a configuration window titled "Call Forwarding Options" with the following settings:

<input type="checkbox"/>	Skip to next extension or phone number after	5	Ring(s)
<input checked="" type="checkbox"/>	Forward Call after waiting	18	Second(s)
	Destination number	*551002	
<input type="checkbox"/>	Call forwarding busy		

User Seats

Seats have a variety of call forwarding options available to them.

1. In the **Customer Admin Portal**, select **Locations**, then the appropriate location (or all locations).
2. Select the seat you wish to adjust and press **Edit**.
3. Go to the **Incoming Calls** tab in the **Manage Phone System** window that just opened.
4. Find the appropriate **Call Forwarding** condition and turn the slider on.
5. Input the destination number or extension.
6. Save to apply these changes.

Manage Settings - 1005 [To change or manage settings, just click on the feature.] ? x

Incoming Calls	Outgoing Calls	Messaging	Call Control	E911 Service	Time Zone
▶ Alternate Numbers (0 Numbers)					
▶ Automatic Hold/Retrieve OFF					
Anonymous Call Rejection OFF					
Priority Alert for External Calls OFF					
▼ Call Forwarding Always ON					
Destination Number / Extension		<input type="text" value="2148675309"/>			
Play ring reminder when call is forwarded.		<input type="checkbox"/>			
▶ Call Forwarding Busy OFF					
▶ Call Forwarding No Answer OFF					
▶ Call Forwarding Not Reachable OFF					

Previous Next Save Cancel

Call Forwarding Conditions

Call Forwarding Always will divert the call to the destination number immediately upon presentation.

Call Forwarding Busy will divert the call only if the line is busy (handling three concurrent calls, or is in **Do Not Disturb** mode). By default, this will go to the **Busy** greeting of the voicemail.

Call Forwarding No Answer will divert the call if it is not answered within the designated number of rings. By default, this will go to the **No Answer** greeting of the voicemail.

Call Forwarding Not Reachable will divert the call if all established endpoints for the seat are offline. You can learn more about **Call Forwarding Not Reachable** in our **Disaster Management** article.